

# User interactions

## Notification:


Notify the user

Drag the "**User notification**" action into the deployment workflow on the right

Enter the Title

Enter the desired message

Specify the display duration in seconds



## User question:

Drag the "**User Question**" action into the deployment workflow on the right

The user can interact with the deployment, depending on the selected options

In this action, depending on the user's response, the following actions are possible:

If "True" go to step: If the user answers the question in the affirmative

If "False" go to step: If the user answers the question in the negative

If "No User" go to step: If no user is logged in to the machine

If "Timeout" go to step: If the user does not respond within the allotted time (in the example above: 300 seconds) 5 min

To define the "**GO TO STEP**" steps, additional actions are required in the "**Deployment Flow.**"



The actions placed behind the Yes and No buttons must be executed correctly.

Responses to questions must be displayed in the deployment logs

The timeout value must be observed.

## User Postpone Option:

This action allows the window to be displayed multiple times if the "False" button is selected.

The user is asked whether to proceed with the deployment, and additional actions are required in the "Deployment Flow" section.

Here, there are two additional options corresponding to the number of times the user can postpone the deployment (accessible by clicking the Options button), as well as an option specifying the action to take if the maximum number of postponements is reached: "If 'Max Postponements Reached' go to step."

Drag the **"User Postpone Option"** action into the deployment workflow on the right

Enter the Title

Enter the desired message

Specify the display time in seconds:

o e.g., 300 sec, 5 min

Enter the number of possible reminders

o e.g., 3

Enter the time interval between each refresh:

o e.g., 900 sec, 15 min

Enter the actions defined for each choice



The actions associated with the **Yes** and **No** buttons must be executed correctly.

The specified time between each retry of the questions must be observed

Responses to the questions must be displayed in the deployment logs

The timeout value must be observed.

---

Revision #1

Created 2026-04-29 19:23:44 UTC by Adrien Thaissen

Updated 2026-04-29 19:23:44 UTC by Adrien Thaissen