

Set the agent to Debug

Medulla / All versions / Public and private SaaS and On-premise / Maintenance

Setting the agent to **DEBUG** mode couldn't be simpler.

Go to the **agentconf.ini** file located at: **C:\Program Files\Medulla\etc\agentconf.ini**

In the **[global]** section

- Change the value **log_level = INFO** to **log_level = DEBUG**
- Change the value **log_level_slxmpp = FATAL** to **log_level_slxmpp = DEBUG**

Revision #1

Created 2026-04-30 07:37:21 UTC by Adrien Thaisse

Updated 2026-04-30 07:37:21 UTC by Adrien Thaisse