


Chapter 3: Kiosk

- [Kiosk](#)
- [Add Profile](#)

Kiosk



When you arrive on the **Kiosk interface main page**, you are immediately directed to the section **Profile List**, located **at the centre of the page**. This is the first thing you will see when you arrive on this page.

The Profile List Section

This section is placed **at the centre of the screen** and displays all user profiles that have already been created. Depending on the number of existing profiles, you can see different information:

Existing profiles

If profiles have already been created, each profile will appear in a list with information such as:

- **Profile Name** : The name given to the profile when it was created.
- **Profile Status** : Whether the profile is **Assets** or **Inactive**.
- **Management Options** : You can edit or delete a profile if necessary.


Nom du profil		État du profil	Actions
devdemo		Actif	<div><div>Supprimer</div><div>Modifier</div></div>

No profiles created

Don't panic, creating a profile is simple and fast. Follow the steps below to add a new profile in Kiosk. We'll do it together, step by step.

[Click here to see...](#)

Add Profile



To create a new profile, start with the area to the left of the page.

A screenshot of the 'Ajouter un nouveau profil' (Add new profile) form in the Medulla interface. The form is located within a sidebar on the left. The main content area shows the form fields: 'Nom du profil:' (Profile name) with a text input field containing 'Nom', and 'État du profil:' (Profile status) with a dropdown menu showing 'Actif'. Below these fields is a section titled 'Gérer les packages' (Manage packages) which includes two columns: 'Packages disponibles' (Available packages) and 'Packages autorisés' (Authorized packages). The 'Packages disponibles' column contains a search bar and a list of packages: 7zip, Firefox, Medulla Agent v3.2.1, Notepad, Thunderbird, and vlc. The 'Packages autorisés' column is currently empty. At the bottom of the 'Gérer les packages' section, there is a 'Source:' dropdown menu set to 'Entity', a list of sources including 'Siveo Medulla', and a 'Créer' (Create) button.

Profile Creation Steps

Click on "Add Profile"

You will find a link entitled **Add a profile**. Click on it to access the profile creation page.

Fill in the creation form

Once on the page, you will see the form to complete in the centre of the screen. This is where you will configure the profile information.

Information to be completed

1. Profile Name

Enter a name for the profile. This name will then appear in the profile list.

Examples: User1, HR Profile.

2. Profile Status

Choose the status of the profile when creating it:

- **Assets** The profile will be operational immediately.
- **Inactive** : The profile will be created but will remain inactive (it will have to be activated later).

3. **Manage packages (associated applications)**

Two blocks are present to manage applications:

- **Available packages** : List of applications you can add.
Use the field "**Search by name...**" to search for a specific application.
- **Allowed packages** : List of applications already added to the profile.
To add an application, select here in **Available packages**. It will then be added in .

4. **Source of applications**

At the bottom of the form, choose the source(s) of the applications to associate:

- **Entity**
- **LDAP**
- **User**

Finalization

Once all the information has been completed, click the button **Create** to validate the profile creation. The new profile will then be added to the *Profile List*, visible in the centre of the home page.

When adding packages to a Kiosk profile, it is essential that the profile is associated with an inventory.

Without this association, the assignment of packages cannot be carried out.

When deploying packages via Convergence, they must also be linked to an inventory.
Without this link, deployment cannot be performed.