

# Add Profile

Menu de démarrage par défaut	Ajouter un profil	
Scripts de post-imaging	Nom du profil	<input type="text"/>
Liste des profils	Description du profil	<input type="text"/>
<b>Ajouter un profil</b>	Ordre des post-installations	
Configuration de l'imaging	Shutdown	Non sélectionné ▼
Gestionnaire de fichiers de réponse sysprep	MountSystem	Non sélectionné ▼
Tous les groupes d'imaging	Check MountSystem	Non sélectionné ▼
Ajouter un groupe d'imaging	DebugImaging	Non sélectionné ▼
	Copy agent	Non sélectionné ▼
	Copy setup complete	Non sélectionné ▼
	Create folder	Non sélectionné ▼
	Copy drivers	Non sélectionné ▼
	Copy sysprep	Non sélectionné ▼
	Postinstall	Non sélectionné ▼
	<input type="button" value="Valider"/>	

A profile includes a set of automatic actions that run after a system image is deployed to a post. These actions automate tasks such as copying files, system configuration, or installing specific elements.

## Access and editing of a profile

From the management interface it is possible to:

- Add New Profile
- Edit an existing profile
- Delete profile if necessary

## List of available post-installation actions

Here are the actions that can be defined in the desired order.

All are disabled by default, you must select them manually if you want to apply them:

- **Shutdown:** turn off the post automatically after all steps have been completed.
- **MountSystem:** mounts system partitions, useful to access certain files before the end of deployment.
- **Check MountSystem:** Check that the system has been installed.
- **DebugImaging:** activates a diagnostic mode to analyze the process of imaging (mainly used by technicians).
- **Copy agent:** copy the Medulla agent on the post, necessary for remote management.
- **Copy setup complete:** add a file or script to the end of installation.

- **Create folder:** creates one or more custom folders on the post.
- **Copy drivers:** copies the necessary drivers to the target machine.
- **Copy sysprep:** installs files related to Windows system preparation (Sysprep).
- **Postinstall:** entry point to execute a script or custom command once the installation is complete.

## Use of the profile

- Create or modify a profile according to the specific needs of your organization or the targeted position.
- Select the desired actions in the appropriate execution order.

**This profile will then be associated with a deployment task, so that the selected steps are automatically applied after installation.**

---

Revision #1

Created 12 May 2025 14:16:00 by DocsAdmin

Updated 12 May 2025 14:16:04 by DocsAdmin